
Software Release Notes

D4K-60 version 1.4.3

This document describes the changes from D4K-60 version 1.4.2 to version 1.4.3.

Affected products

The following products are affected.

- D4K2560
- D4K3560
- Mirage 4K25
- Mirage 4K35

Purpose of release

The primary purpose of this software release is:

- Fixed an issue with the liquid cooling flow meter not correctly reporting a warning of zero (0) flow.
- Added ability to report temperature on the projector using Fahrenheit:
 - Using the LOC+TEMP serial command:
 - (LOC+TEMP 0)—Enables Celsius reporting
 - (LOC+TEMP 1)—Enables Fahrenheit reporting
 - From the General Settings menu on the touch panel controller (TPC).

The projector must be restarted for the change to take effect.
- Fixed an issue with the Blue Y-Coordinate being changed when starting the projector.

Technical support

Technical support for Christie products is available at:

- North and South America: +1-800-221-8025 or Support.Americas@christiedigital.com
- Europe, Middle East, and Africa: +44 (0) 1189 778111 or Support.EMEA@christiedigital.com
- Asia Pacific: +65 6877-8737 or Support.APAC@christiedigital.com